

# Neuron ISI Firmware update

Revision 1  
2020.06.29

[Prerequisites](#)

[Hardware](#)

[Software](#)

[Installation](#)

## Prerequisites

### Hardware

FT-Click 6050  
U10

### Software

*The software requires windows (tested in windows 10)*

*Download NodeUtil utility provided by Echelon:*

*<https://www.echelon.com/software-downloads?ele=153-0373-01A> and uncompress it.*


*Crom: <https://github.com/izot/shortstack/tree/master/microserver/standard>*

*download the following files:*

- SS430\_FT6050ISI\_SYS20000kHz.apb
- SS430\_FT6050ISI\_SYS20000kHz.h
- SS430\_FT6050ISI\_SYS20000kHz.map
- SS430\_FT6050ISI\_SYS20000kHz.ndl
- SS430\_FT6050ISI\_SYS20000kHz.nei
- SS430\_FT6050ISI\_SYS20000kHz.nme
- SS430\_FT6050ISI\_SYS20000kHz.nmf
- SS430\_FT6050ISI\_SYS20000kHz.sym
- SS430\_FT6050ISI\_SYS20000kHz.xif

# Installation

You have to connect the FT-10 to the FTclick to program it, with 2 wires (no polarity)



Go to the folder containing NodeUtil.exe.

Copy the firmware files into the same folder to make it easy.

Execute nodeutil.exe

In the prompt press option f to find devices, or press service ft-click button.

Press g and 1 to choose the ft-click device

Press y to upload the firmware and write the firmware

filename:SS430\_FT6050ISI\_SYS20000kHz.ndl

Press N to the overriding configuration question.

Press e twice to exit.